

# Windtunnel Software (+ UtilitiesShare-Repo)

Short overview on  
Features, Logic and Settings  
and use of Repository

WTSOftwareUtilitiesSharePublic

main

1 Branch

0 Tags

Go to file

Add file

Code

se04ber

Fix removing caching for deploy file, to prevent new changes not bein...1915156 · 2 weeks ago45 Commits

Data

Add percentage Option and visualization to convergence plotlast month

ExampleData

Fix removing caching for deploy file, to prevent new change...2 weeks ago

Results

Add percentage Option and visualization to convergence plotlast month

\_\_pycache\_\_

Add percentage Option and visualization to convergence plotlast month

windows\_deploy

config\_name, uncertaintyIs splitting, convergence plot, depl...last month

windtunnel

Fix removing caching for deploy file, to prevent new change...2 weeks ago

Example\_Flow\_Analysis.ipynb

Fine tune convergence plotlast month

Example\_PointConc\_Analysis\_200325\_Analy...

Fix removing caching for deploy file, to prevent new change...2 weeks ago

Example\_PointConc\_Analysis\_200325\_Analy...

Add percentage Option and visualization to convergence plotlast month

Example\_PointConc\_Analysis\_200325\_Maps...

Small changes to notebooks2 months ago

Example\_PointConc\_Analysis\_200325\_Origin...

Split Notebooks into 4 depending on task and some fixes4 months ago

Example\_PointConc\_Analysis\_200325\_stepB...

Small changes to notebooks2 months ago

README.md

Update READMElast month

combined\_data.csv

Split Notebooks into 4 depending on task and some fixes4 months ago

deploy\_config.py

Fix removing caching for deploy file, to prevent new change...2 weeks ago

requirements.txt

Add requirements file3 months ago


setup.py

readd setup for notebook interactionlast month


windtunnel.log

Fix decimal points to 62 weeks ago


# Convergence plots



Bandwidth Convergence: UBA\_GA\_02\_04\_01\_000\_1\_001 - UBA\_GA\_02\_04\_01\_000\_1\_001.txt.ts#0



Convergence Test: UBA\_GA\_02\_04\_01\_000\_1\_001 - UBA\_GA\_02\_04\_01\_000\_1\_001.txt.ts#1




# Flow\_Analysis Notebook




## Convergence Test:

Bandwidth of means for different averaging intervals




## Vertical/Horizontal Wind Profiles:

Mean velocity( $U$ ) and turbulence intensity ( $I_u, I_v, I_w$ ) vertically




## Boundary Layer Fitting:

Power law exponent  $\alpha$  and roughness length  $z_0$




## Turbulence Statistics:

Reynolds stresses vertically





## Integral Length Scales:

Lux from autocorrelation



## Spectral Analysis:


Power spectral density of velocity fluctuations



# Concentration analysis Notebook

All raw Ts files read-in into PointConc-object, postprocessing logic to (c\_net[ppmV],c[-],c\_fs[ppmV]) saved into array conc\_ts[prefix][file]

Basic overview and distribution plots:  
(Mean,Stdev, 95percentile, Peak/Mean)-Table,Full ts plot, Means, Pdfs,Cdfs, Histograms, Boxplot, ViolinPlot



Next: Your Analysis (..) :)

# Repository structure



**Main Logic:** package windtunnel/  
concentration/ ( [PointConcentration.py](#), PuffConcentration.py )  
flow/  
plots/, grid/  
timeseries.py



**Deployment files**  
(deploy\_config.py - Jupyterhub server connection)  
windows\_deploy/, requirements.txt)




## Jupyter Notebooks

Flow\_Analysis.ipynb - Interactive plotting of routine wind flow configuration check plots  
Example\_PointConc\_Analysis.ipynb - Interactive reading-in, postprocessing and plotting of concentration  
(Analysis, Analysis\_deploy, stepByStep, Map) (Local machine version, JupyterHub version, Learning version, Map plotting version)



## Data Folder

Data/InputData/ - Raw measurement time series  
Data/ParameterFiles/ - CSV files with ambient/(configuration) conditions/settings  
Results/ - Usually default results output folder  
ExampleData/ - Example time series files for testing



File	Commit Message	Time
Data	Add percentage Option and visualization to convergence plot	last month
ExampleData	Fix removing caching for deploy file, to prevent new change...	2 weeks ago
Results	Add percentage Option and visualization to convergence plot	last month
_pycache_	Add percentage Option and visualization to convergence plot	last month
windows_deploy	config_name, uncertainty splitting, convergence plot, depl...	last month
windtunnel	Fix removing caching for deploy file, to prevent new change...	2 weeks ago
Example_Flow_Analysis.ipynb	Fine tune convergence plot	last month
Example_PointConc_Analysis_200325_Analy...	Fix removing caching for deploy file, to prevent new change...	2 weeks ago
Example_PointConc_Analysis_200325_Analy...	Add percentage Option and visualization to convergence plot	last month
Example_PointConc_Analysis_200325_Map...	Small changes to notebooks	2 months ago
Example_PointConc_Analysis_200325_Orig...	Split Notebooks into 4 depending on task and some files	4 months ago
Example_PointConc_Analysis_200325_stepB...	Small changes to notebooks	2 months ago
README.md	Update README	last month
combined_data.csv	Split Notebooks into 4 depending on task and some files	4 months ago
deploy_config.py	Fix removing caching for deploy file, to prevent new change...	2 weeks ago
requirements.txt	Add requirements file	3 months ago
setup.py	read setup for notebook interaction	last month
windtunnel.log	Fix decimal points to 6	2 weeks ago

# Deployment choices

<p>1.Linux/Mac/Windows: <b>Quick-Start Option/Manual</b></p> <p>Use the notebook online in the JupyterHub UUH server</p> <p>No python package local installations needed, but no change of windtunnel folder possible</p>	<p>2.Windows: <b>Quick-Start Option/Manual</b></p> <p>Install package locally, but with use of helper scripts</p> <p>In two clicks, creates a clean environment "WTConc2", installs python dependencies, and runs the notebooks</p>	<p>3.Linux/Mac/Windows: <b>Quick-Start Option/Manual</b></p> <p>Install package locally, manually</p> <p>(Clone repo manually and create a clean environment "WTConc2", install python dependencies, and run the notebooks manually) Git needed)</p>
---	---	--

# Quick Start Options

---

## Option 1: Jupyter Server (Recommended for Students)

**Best for:** Using the notebook on a (f.e. the UHH) Jupyter Notebook online server without installing the full package.

**Requirements:** Jupyter Notebook server access

### Steps:

1. Upload two files to your Jupyter server:

- `Example_PointConc_Analysis_200325_Analysis_deploy.ipynb`
- `deploy_config.py`

2. Open the notebook and run the first cell. The notebook will:

- Automatically install the `windtunnel` package from GitHub
- Create the necessary folder structure ( `Data/InputData/` , `Data/ParameterFiles/` , `Results/` )
- Download example data

## Option 2: Full Installation: Windows Local using scripts

**Best for:** Installing, running and maybe editing or contributing to the full repository locally on Windows. When changes in the project folder should be made. Creates a clean environment "WTConc2" and runs notebooks in it with two clicks using helper scripts.

### Requirements:

- Python >3.6 installed
- (Git installed (or download repository manually as ZIP from GitHub))

### Steps:

#### 1. First-time setup (run once):

```
Run windows_deploy\setup_WTConc2.bat
```



This creates a virtual environment `WTConc2` and installs all dependencies from `requirements.txt`.

#### 2. Start Jupyter Notebook (every time you want to use it):

```
Run windows_deploy\Start_WTConc2_Notebook.bat
```



3. Open any notebook f.e. `Example_PointConc_Analysis_200325_Analysis.ipynb` in the opened jupyter folder tree.



### Option 3: Full Installation: Manually

**Best for:** Not Windows users who want to install, run and maybe edit the full project folder logic locally, contribute etc. Only the pip packages in requirements.txt need to be set up.

#### Requirements:

- Python >3.6 installed
- Git installed

#### Steps:

##### 1. Clone the repository:

```
git clone https://github.com/se04ber/WTSOFTWAREUTILITIESSHARE.git  
cd WTSOFTWAREUTILITIESSHARE
```



##### 2. Create a virtual environment:

```
python -m venv WTConc2
```



##### 3. Activate the environment:

###### ◦ Windows:

```
WTConc2\Scripts\activate
```



###### ◦ Linux/Mac:

```
source WTConc2/bin/activate
```



##### 4. Install dependencies:


```
pip install -r requirements.txt
```



# General structure of the notebooks

1. **Cell 0(Deploy): deploy setup and Data-path setup**
2. Cell 1: Paths and settings
3. Cell 2: Default csv parameter file values
4. Cell 3: Main Logic
5. Cell 4: Output testing
6. Cell 5: Bandwidth Convergence plot
7. Cell 6-: Basic Distribution analysis plots or flow plots
8. Your analysis and plots :)

# JupyterHub version

 deploy\_config.py

16d ago

 Example\_PointC...

13d ago

```
: # Windtunnel Package Setup
from deploy_config import install_windtunnel, verify_installation

# Install and verify windtunnel package
if not install_windtunnel():
    print("❌ Installation failed. Please check your internet connection.")
else:
    verify_installation()
```

📦 Installing windtunnel package from GitHub...

Defaulting to user installation because normal site-packages is not writeable

Collecting [git+https://github.com/se04ber/WTSoftwareUtilitiesShare.git](https://github.com/se04ber/WTSoftwareUtilitiesShare.git)

Cloning <https://github.com/se04ber/WTSoftwareUtilitiesShare.git> to /tmp/pip-req-build-b3034m2

Running command `git clone --filter=blob:none --quiet https://github.com/se04ber/WTSoftwareUtilitiesShare.git /tmp/pip-req-build-b3034m2`

Resolved <https://github.com/se04ber/WTSoftwareUtilitiesShare.git> to commit f91515e393e77c883ba29b82ed21b763acc78349

Preparing metadata (setup.py): started

# Data source configuration

USE\_GITHUB\_EXAMPLE\_DATA = True #False #True # Set to False to use local data

#Else use your own Data in Folder Data/(your\_data\_folder)/measurement\_prefix\*, ...

DATA\_FOLDER\_NAME = "UBA Konvergenz" #name of folder inside Data/InputData/ f.e. Umrechnung zur Kontrolle /

PARAMETER\_FILE\_NAME = "ambient\_conditions.csv" #name of parameterFile inside ParameterFiles f.e. ambient\_conditions\_.UBA\_GA.csv

MEASUREMENT\_PREFIX = "your\_measurement\_prefix" #Prefix of all time series files inside DATA\_FOLDER\_NAME f.e. UBA\_GA\_02\_04\_01\_000\_1\_00

# Data Setup and Configuration

from deploy\_config import setup\_folder\_structure, setup\_github\_data, setup\_local\_data

# Setup folder structure and data

base\_dir, data\_dir, input\_dir, param\_dir, results\_dir = setup\_folder\_structure()

if USE\_GITHUB\_EXAMPLE\_DATA:

path\_dir, path, csv\_file, output\_path, namelist = setup\_github\_data(input\_dir, param\_dir, results\_dir)

else:

# Local data configuration

DATA\_FOLDER\_NAME = DATA\_FOLDER\_NAME

PARAMETER\_FILE\_NAME = PARAMETER\_FILE\_NAME

MEASUREMENT\_PREFIX = MEASUREMENT\_PREFIX

path\_dir, path, csv\_file, output\_path, namelist = setup\_local\_data(

input\_dir, param\_dir, results\_dir, DATA\_FOLDER\_NAME, PARAMETER\_FILE\_NAME, MEASUREMENT\_PREFIX

)

print(f"✅ Setup complete! Data path: {path}, Output: {output\_path}")

📁 Setting up folder structure...

✅ Created directory: /home/jovyan/Data

✅ Created directory: /home/jovyan/Data/InputData

✅ Created directory: /home/jovyan/Data/ParameterFiles

✅ Created directory: /home/jovyan/Results

🌐 Using GitHub example data

📦 Downloading example data from GitHub...

# General structure of the notebooks

1. Cell 0(Deploy): deploy setup and Data-path setup
2. **Cell 1: Paths and settings**
3. Cell 2: Default csv parameter file values
4. Cell 3: Main Logic
5. Cell 4: Output testing
6. Cell 5: Bandwidth Convergence plot
7. Cell 6-: Basic Distribution analysis plots or flow plots
8. Your analysis and plots :)

# Paths and settings

- ❑ path\_dir = “(...) / WTSoftwareUtilitiesShare”
- ❑ path = “(...) / InputData / specificFolder”
- ❑ output\_path = “(...) / ExampleData / Results”
- ❑ namelist = [“UBA\_GA\_001”]
- ❑ csv\_file = “UBA\_parameters.csv”
- ❑ parameters\_PerFolder = False/True
- ❑ full\_scale = “ms” / “fs” / “nd”
- ❑ osType = “Linux” / “Windows” #For Path
- ❑ outputName = None #Default: ts name
- ❑ saveTs=True,
- ❑ saveAvg=True,
- ❑ saveStats=True
- ❑ saveCombined=True
- ❑ combinedFileName=“combined\_file\_nora.csv”
- ❑ base\_path=Files/Point\_Data\_stats/UBA\_thesis
- ❑ saveAll=True

```
#INPUT
path_dir = "/home/sabrina/Desktop/Schreibtisch/Arbeit_2025/WTSoftwareUtilitiesShare"
#Path to your input data
#path = f"{path_dir}/ExampleData/InputData/Concentration/"
path = f"{path_dir}/ExampleData/InputData/Beispiel Umrechnung zur Kontrolle/"
#path = f"/home/sabrina/Schreibtisch/Arbeit_2025/Nora_test/"
# Name of your measurement files prefix
#namelist = ['BFS_BD3_MP01_000']
namelist = ['UBA_GA_02_04_01_000_1_001'] #['UBA_thesis']
#Path to your output folder for average files and plots
output_path = f"{path_dir}/ExampleData/Results/"
#For PointData for the functions to work the columns of the file should be: time, wtfref, slow_FID, fast_FID, open_rate
#(See manual for the description of the variables)
#Name of csv file which contains ambient conditions data. Multiple diff. ambient conditions for diff datasets can be read-in at ones
#If no file given or configuration wrong, the program resorts to try reading-in given values manually below.
#csv_file='ambient_conditions.csv'
#csv_file= f"{path_dir}/ExampleData/ParameterFiles/ambient_conditions.csv"
csv_file= f"{path_dir}/ExampleData/ParameterFiles/ambient_conditions_UBA_GA.csv"
#csv_file= f"{path_dir}/ambient_conditions_pointl.csv"
parameters_PerFolder = False

#Variables and Parameters set for all ts, if no ambient_conditions.csv file overgiven
#If at the end calculate entdimensionalised or full scale transform quantities
#Default: nd:entdimensionalise, ms:model scale, fs:full scale.
full_scale='ms'
#Postprocessing before analysis
applyPostprocessing=True
averageInterval=60 #s #Interval to downaverage raw time series to before analysis
measurementFreq=0.005 #Time series frequency #For now only for static case implemented
averagingColumns=["net_concentration"] #Columns to average dow
#Saving settings: (output_path for path)
osType = "Linux" #Windows #For Path
outputName = None #Default: ts name

saveTs=True #Only save time series of concentration quantities to separat files
saveAvg=True #Save average of ts of concentration quantities to separat files
saveStats=True #Save averages, percentile95/5, peak2mean of ts of concentration quantities to separat files
saveCombined=True #Save all averages and statistics for all files to one combined file
combinedFileName="combined_file_nora.csv"
base_path=None #base_path = output_path + "Files/Point_Data_stats/UBA_thesi/" # Base path for getting files for combined files, if None

saveAll=True #Sets saveTs, saveAvg and saveStats, saveCombined to True, saving ts, averages, statistics and combined file
```

**Data/InputData/UBA/**

UBA\_GA\_001\_ts#1

UBA\_GA\_001\_ts#2

UBA\_GA\_001\_ts#3

....

**Data/ParameterFiles/**

UBA\_parameters.csv

# General structure of the notebooks

1. Cell 0(Deploy): deploy setup and Data-path setup
2. Cell 1: Paths and settings
3. **Cell 2: Default csv parameter file values**
4. Cell 3: Main Logic
5. Cell 4: Output testing
6. Cell 5: Bandwidth Convergence plot
7. Cell 6-: Basic Distribution analysis plots or flow plots
8. Your analysis and plots :)

# Parameterfile

- |                          |                            |                 |
|--------------------------|----------------------------|-----------------|
| <input type="checkbox"/> | x/y/z_source=(?,?,?)       | [mm]            |
| <input type="checkbox"/> | x/y/z_measure=(?,?,?)      | [mm]            |
| <input type="checkbox"/> | mass_flow_controller=0.300 | [l/h]           |
| <input type="checkbox"/> | calibration_curve=1.0      | [-]             |
|                          | calibration_factor=0.0     | [-]             |
| <input type="checkbox"/> | gas_name="C12"             | [-]             |
| <input type="checkbox"/> | gas_factor=0.5             | [-]             |
| <input type="checkbox"/> | mol_weight=29.0            | [g/mol]         |
| <input type="checkbox"/> | pressure=101426.04472      | [Pa]            |
| <input type="checkbox"/> | temperature=23             | [°C]            |
| <input type="checkbox"/> | scale=400                  | [Model/Reality] |
| <input type="checkbox"/> | scaling_factor=0.5614882   | [Model/Reality] |
| <input type="checkbox"/> | ref_length=1/400           |                 |
| <input type="checkbox"/> | ref_height=100/400         |                 |
| <input type="checkbox"/> | full_scale_wtref=10        | [m/s]           |
| <input type="checkbox"/> | full_scale_flow_rate=0.002 | [kg/s]          |
| <input type="checkbox"/> | full_scale_temp=20         | [°C]            |
| <input type="checkbox"/> | full_scale_pressure=101325 | [Pa]            |
| <input type="checkbox"/> | config_name="test"         | [-]             |

```
#Example file/Default environment values if no csv_file found:
```

```

Source location [mm]
x_source=0
y_source=0
z_source=0

#Source mass flow controller, calibration settings
mass_flow_controller=0.300 #0.600#Stickstoffdurchflussregler #[l/h]*1/100 #'X' #Controller(settings) used, just a name placeholder for orientation
#If calibration performed on a controller, corrects actual max. flow capacity of controller
calibration_curve=1.0 #0.3 #0.3 oder 3
calibration_factor=0.1 #

#Gas characteristics
gas_name='C12' #Just placeholder name variable for orientation, not used for anything
gas_factor=0.5 #-] #!!! Needs to be calculate/specificate f.e. if gas changes
mol_weight=29.0 #28.97 #Air [g/mol]
#Measurement location [mm]
x_measure=1020 #855.16
y_measure= 0 #176.29
z_measure= 5 #162
#Surrounding conditions
pressure=101426.04472 #1009.30 #[hPa] ->Pa
temperature=23 #23.5 #[°C]
#Model to Reality scaling
scale=400 #250 #Model/Reality
scaling_factor=0.5614882 #0.637 #USA1 to selected ref pos.?
ref_length=1/400 #1/250 #Lref
ref_height=100/400 #None #Href
#Full Scale Parameters
full_scale_wtref=10 #6 #Uref fullscale
full_scale_flow_rate=0.002 #Q_amb[kg/s]? #0.5 #Qv_fullscale
full_scale_temp=20 #[°C]
full_scale_pressure=101325 #[Pa]
#0_ambient[kg/s] -> Q[m³/s]=Q[kg/s]/R*T/(M*P)
#Variable wdir for wind direction. To be implemented in future. ##
#wdir=0
#Variable axis range. Reserved for future implementation of axis range specification,
#analogously to puff mode
#axis_range='auto'

```

[illegible]

# General structure of the notebooks

1. Cell 0(Deploy): deploy setup and Data-path setup
2. Cell 1: Paths and settings
3. Cell 2: Default csv parameter file values
4. **Cell 3: Main Logic**
5. Cell 4: Output testing
6. Cell 5: Bandwidth Convergence plot
7. Cell 6-: Basic Distribution analysis plots or flow plots
8. Your analysis and plots :)



# Main Logic - mass flow rate

- ❑ model scale  
ambient mass flow rate Q

$$\dot{Q}_{\text{amb}} = \frac{\text{open\_rate} \cdot 10 \cdot f_{\text{gas}} \cdot \dot{Q}_{\text{controller}}}{100} \cdot \frac{T_K \cdot p_{\text{std}}}{p \cdot T_{\text{std},K}}$$

- ❑ Qcontroller = Maximum flow rate capacity of gate (150l/h)
- ❑ Multiplied with  
open\_rate[1-10] of gate  
(ts file) and gas factor  
and ambient conditions(T,p)

- $\dot{Q}_{\text{amb}}$  – ambient mass flow rate [l/h]
- open\_rate – valve opening [0-10], multiplied by 10 to get percentage
- $f_{\text{gas}}$  – gas correction factor [-] (e.g., for different tracer gases)
- $\dot{Q}_{\text{controller}}$  – maximum flow rate of mass flow controller [l/h]
- $T_K$  – ambient temperature [K]
- $p$  – ambient pressure [Pa]
- $T_{\text{std},K}$  – standard temperature = 273.15 K
- $p_{\text{std}}$  – standard pressure = 101325 Pa

# Main Logic - Net Concentration

❑ net\_concentration C [ppmV]

$$C_{\text{net}} = \text{fast\_FID} - \text{slow\_FID}$$

❑ slow\_FID - total concentration measured by fast flame ionization detector

❑ fast\_FID - background concentration [ppmV]

# Main Logic - Entdimensionalised Concentration

- Entdim. concentration  $C$  [-]
- Comparing measurements at different scales and conditions

$$C^* = \frac{C_{\text{net}} \cdot \bar{U}_{\text{ref}} \cdot L_{\text{ref}}^2}{\dot{Q}_{\text{amb}}}$$

- $C^*$  – dimensionless concentration [-]
- $C_{\text{net}}$  – net concentration [ppmV], converted to volume fraction by  $10^{-6}$
- $\bar{U}_{\text{ref}}$  – mean reference wind speed [m/s]
- $L_{\text{ref}}$  – reference length (model scale) [m]
- $\dot{Q}_{\text{amb}}$  – ambient flow rate [l/h], converted to [m<sup>3</sup>/s] by  $(1000 \cdot 3600)^{-1}$

$$C^* = \frac{\left(\frac{C_{\text{net}}}{10^6}\right) \cdot \bar{U}_{\text{ref}} \cdot L_{\text{ref}}^2}{\left(\frac{\dot{Q}_{\text{amb}}}{1000 \cdot 3600}\right)}$$

# Main Logic

```
conc_ts[name][file] = wt.PointConcentration.from_file(path + file)

conc_ts[name][file].ambient_conditions(x_source=x_source, y_source=y_source, z_source=z_source,
                                       x_measure=x_measure, y_measure=y_measure, z_measure=z_measure,
                                       pressure=pressure,
                                       temperature=temperature,
                                       calibration_curve=calibration_curve,
                                       mass_flow_controller=mass_flow_controller,
                                       calibration_factor=calibration_factor,
                                       config_name=config_name)

#Set read-in scaling, gas and full scale information to internal class variables
print("Store information into PointConcentration class objects array")
conc_ts[name][file].scaling_information(scaling_factor=scaling_factor,
                                       scale=scale,
                                       ref_length=ref_length,
                                       ref_height=ref_height)

conc_ts[name][file].tracer_information(gas_name=gas_name,
                                       mol_weight=mol_weight,
                                       gas_factor=gas_factor)

conc_ts[name][file].full_scale_information(full_scale_wtref=full_scale_wtref,
                                       full_scale_flow_rate=full_scale_flow_rate,
                                       full_scale_temp=full_scale_temp, full_scale_pressure=full_scale_pressure)

#Calculate mass flow rate, net concentration and dimensionalise concentration
print("Do main calculations")
conc_ts[name][file].convert_temperature()
conc_ts[name][file].calc_wtref_mean()

conc_ts[name][file].calc_model_mass_flow_rate(usingMaxFlowRate="True", applyCalibration="False")
conc_ts[name][file].calc_net_concentration()

#conc_ts[name][file].clear_zeros() #Remove values net_concentration =< 0 from dataset !noise
conc_ts[name][file].calc_c_star()

conc_ts[name][file].calc_full_scale_concentration() #Try
```

# Main Logic

```
conc_ts[name][file] = wt.PointConcentration.from_file(path + file)

conc_ts[name][file].ambient_conditions(x_source=x_source, y_source=y_source, z_source=z_source,
                                       x_measure=x_measure, y_measure=y_measure, z_measure=z_measure,
                                       pressure=pressure,
                                       temperature=temperature,
                                       calibration_curve=calibration_curve,
                                       mass_flow_controller=mass_flow_controller,
                                       calibration_factor=calibration_factor,
                                       config_name=config_name)

#Set read-in scaling, gas and full scale information to internal class variables
print("Store information into PointConcentration class objects array")
conc_ts[name][file].scaling_information(scaling_factor=scaling_factor,
                                       scale=scale,
                                       ref_length=ref_length,
                                       ref_height=ref_height)

conc_ts[name][file].tracer_information(gas_name=gas_name,
                                       mol_weight=mol_weight,
                                       gas_factor=gas_factor)

conc_ts[name][file].full_scale_information(full_scale_wtref=full_scale_wtref,
                                       full_scale_flow_rate=full_scale_flow_rate,
                                       full_scale_temp=full_scale_temp, full_scale_pressure=full_scale_pressure)

#Calculate mass flow rate, net concentration and dimensionalise concentration
print("Do main calculations")
conc_ts[name][file].convert_temperature()
conc_ts[name][file].calc_wtref_mean()

conc_ts[name][file].calc_model_mass_flow_rate(usingMaxFlowRate="True", applyCalibration="False")
conc_ts[name][file].calc_net_concentration()

#conc_ts[name][file].clear_zeros() #Remove values net_concentration =< 0 from dataset !noise
conc_ts[name][file].calc_c_star()

conc_ts[name][file].calc_full_scale_concentration() #Try
```

# Main Logic

```
conc_ts[name][file] = wt.PointConcentration.from_file(path + file)

conc_ts[name][file].ambient_conditions(x_source=x_source, y_source=y_source, z_source=z_source,
                                       x_measure=x_measure, y_measure=y_measure, z_measure=z_measure,
                                       pressure=pressure,
                                       temperature=temperature,
                                       calibration_curve=calibration_curve,
                                       mass_flow_controller=mass_flow_controller,
                                       calibration_factor=calibration_factor,
                                       config_name=config_name)

#Set read-in scaling, gas and full scale information to internal class variables
print("Store information into PointConcentration class objects array")
conc_ts[name][file].scaling_information(scaling_factor=scaling_factor,
                                       scale=scale,
                                       ref_length=ref_length,
                                       ref_height=ref_height)

conc_ts[name][file].tracer_information(gas_name=gas_name,
                                       mol_weight=mol_weight,
                                       gas_factor=gas_factor)

conc_ts[name][file].full_scale_information(full_scale_wtref=full_scale_wtref,
                                       full_scale_flow_rate=full_scale_flow_rate,
                                       full_scale_temp=full_scale_temp, full_scale_pressure=full_scale_pressure)

#Calculate mass flow rate, net concentration and dimensionalise concentration
print("Do main calculations")
conc_ts[name][file].convert_temperature()
conc_ts[name][file].calc_wtref_mean()

conc_ts[name][file].calc_model_mass_flow_rate(usingMaxFlowRate="True", applyCalibration="False")
conc_ts[name][file].calc_net_concentration()

#conc_ts[name][file].clear_zeros() #Remove values net_concentration =< 0 from dataset !noise
conc_ts[name][file].calc_c_star()

conc_ts[name][file].calc_full_scale_concentration() #Try
```

# Main Logic

❏ Transform to scale

❏ Save files  
(ts: c\_net,c\*,c\_fs)  
(avg: ..)  
(stats: peak2Mean,  
percentiles)

```
#Transforming/Outputting data in full-scale, model scale, and non-dimensional
print("Transform scale")
if full_scale == 'ms':
    dict_conc_ts = conc_ts

elif full_scale == 'fs':
    dict_conc_ts = conc_ts_fs
    dict_conc_ts[name][file].to_full_scale()

elif full_scale == 'nd':
    dict_conc_ts = conc_ts_nd
    dict_conc_ts[name][file].to_non_dimensional()
else:
    print(
        "Error: invalid input for full_scale. Data can only be computed in model scale (full_scale='ms'), full scale (full_scale='fs'), or non-dimensional (full_scale='nd'). Please check the input."
    )
    #Apply Postprocessing if overgiven

for file in files:
    if(saveTs):
        if full_scale == 'ms':
            dict_conc_ts[name][file].save2file_ms(file, out_dir=output_path + folder)
        elif full_scale == 'fs':
            dict_conc_ts[name][file].save2file_fs(file, out_dir=output_path + folder)
        elif full_scale == 'nd':
            dict_conc_ts[name][file].save2file_nd(file, out_dir=output_path + folder)
        else:
            print(
                "Error: invalid input for full_scale. Data can only be computed in model scale (full_scale='ms'), full scale (full_scale='fs'), or non-dimensional (full_scale='nd'). Please check the input."
            )
            exit
        print("Created ts files including (net_concentration, entimendionsliased and full scale concentration)")
    if(saveAvg):
        #Saving averages to files under folder Point_Data_stats/
        #Averages of net_concentration,c_star and full_scale_concentration
        wt.check_directory(output_path + folder_avg)
        dict_conc_ts[name][file].save2file_avg(file, out_dir=output_path + folder_avg)
        print(f"Created avg files under {output_path + folder_avg}")
    if(saveStats):
        #Saving stats to files under folder Point_Data_avg/
        #Stats Full ausgabe: saveAvg Quantities + Percentile 95, percentile 5, peak2Mean of net_concentration_c_star and full_Scale_...
        wt.check_directory(output_path + folder_stats)
        dict_conc_ts[name][file].save2file_fullStats(file, out_dir=output_path + folder_stats)
        print(f"Created stats files under {output_path + folder_stats}")

if(saveCombined):
    from windtunnel.concentration.utils import combine_to_csv2
    stats=True
    if(stats):
        file_type="stats"

    file_names = ["_stats_" + file for file in files]
    if(base_path==None):
        base_path = output_path + f"Files/Point_Data_{file_type}/{name[0:-1]}/"
```



# General structure of the notebooks

1. Cell 0(Deploy): deploy setup and Data-path setup
2. Cell 1: Paths and settings
3. Cell 2: Default csv parameter file values
4. Cell 3: Main Logic
5. **Cell 4: Output testing**
6. **Cell 5: Bandwidth Convergence plot**
7. **Cell 6-: Basic Distribution analysis plots or flow plots**
8. **Cell (-,-): Your analysis and plots :)**



# Next Cells

- ❏ Read into Help-Array for plotting, Overview on stats quantitatively
- ❏ Then: Called plotting functions with defined settings for each cell (basic distribution plots)
- ❏ Next Cells: your own project specific analysis and plots :)

```
DataPointsConc = []  
#DataPointsConc = [ conc_ts[namelist[0]]["MyFileofInterest1.txt"], conc_ts[namelist[0]]["MyFileofInterest2.txt"]]  
for i in range(len(files)): #Just visualising all  
    data = conc_ts[namelist[0]][files[i]]  
    DataPointsConc.append(data)  
# Richtige Zeitserien laden  
labels=[f"Dataset {i}" for i in range(0,len(DataPointsConc))]  
plot_timeseries_with_stats(DataPointsConc,dimensionless=dimensionless,labels=labels,color=color)
```

```
File: UBA_GA_02_04_01_000_1_001.txt.ts#0  
c_star vorhanden  
C_star shape: (30000,)  
NaNs vorhanden: False  
Min/Max: -0.30316299999999985 / 1202.017763  
Mean: 57.80034634370001  
Std: 57.766640161132536  
Percentiles: {10: 12.215996500000001, 90: 120.00919130000001, 95: 161.68999759999997}
```

```
[15]: xLabel="Datasets"  
      yLabel="Concentration[ppmV]"  
      xLabel="Datasets"  
      yLabel="Concentration[ppmV]"  
      create_histogram(DataPointsConc,dimensionless="False",labels=None,xLabel=xLabel,yLabel=yLabel,xAchse=None,yAchse=None)
```